# Connect to C\$

Last Modified on 08.31.23

The **Connect to C\$** tool opens the client's C drive in a local Windows Explorer window.

This tool uses the hidden admin share (C\$). This hidden admin share must remain enabled.

To run the tool:

1. In your Configuration Manager console, right-click on a device.

2. Click Right Click Tools > Console Tools > Connect to C\$.

#### Port Requirements

TCP445 must allow network traffic from the device running the Configuration Manager console to the device being connected to.

## **Recast Permissions**

Requires the Open C\$ Share permission in the Local Actions plugin.

### **Microsoft Permissions**

This action runs using the credentials of the user signed into the Configuration Manager. That user requires permission to browse the C\$ Share on the remote device, which typically means that the user requires administrator permissions on the remote device. Permissions cannot be elevated with Recast Agent or Recast Proxy.

**NOTE**: This is the case even if using Recast Management Server with a service account because this action launches an application outside of Recast. If the user does not have permission, a prompt will open asking for a username and password to try to successfully connect to the remote device.

To work around the limitations associated with these permissions, you can set up an alternative Explorer Shell.

#### Alternative Explorer Shell Setup

Specifying an alternative Windows Explorer shell will cause this tool to launch that application instead of Windows Explorer when trying to connect to the remote filesystem. When using the alternative shell, Recast will not prompt for credentials if it detects the user does not have permission — it will let the alternative shell handle this scenario.

To specify an alternate Explorer shell:

1. In your Configuration Manager console, navigate to Assets and Compliance > Recast Software.

2. Click Configure Recast in the 'How Can We Help?' section.

← → ▼ ( ● \ → Assets and Compliance →	Overview       Recast Software				
Assets and Compliance <					
Sers					
		iols re feature set of 80+ tools included in 1 out of our tools. If you have questions	Installation Information Desktop Installed Version: Server Installed Version: Enterprise License: License Expiration Date: Remote Server Status:	ON 5.2.2307.703 5.2.2307.703 V 8/7/2023 Connected Recast Software	
Conclusion Retering     Compliance Settings     Compliance Settings     Compliance Settings     Compliance Settings     All Corporate-owned Devices     Recast Software	Getting Started Check out some of our most used too productivity, and automate complex of	ols and dashboards created to surface workflows.	License Org: How Can We Help?		
Assets and Compliance	Software Update Deployment Status (SUDS) Run a highly-targeted scan of software update deployment compliance, returning results in two categories: compliance by device and non-compliant devices by update category.	LAPS Dashboard Surfaces compliance data about the Microsoft LAPS tool. The scan can be directed at a specific Domain, OU, and/or Collection. Results are returned in a simple LAPS Present/Not Present chart Expand this node to view the	Active Directory Cleanup Dashboard Scans Configuration Manager and Active Directory for devices, showing results about where those devices are: in just ConfigMg; just AD, or (properly) in both.	Configure Recast	Contact Support
Administration	Expand this node to view the dashboard Enterprise Tool	dashboard Enterprise Tool	Expand this node to view the dashboard Enterprise Tool	Documentation	Enterprise Portal

#### 3. On the **Windows Explorer** tab, enter the **Local Path** or click **Browse** to navigate to the application.

	-		ole Extension			_		×
General	Licensing	SQL	Wake On Lan	Windows Explorer	Service Now	Interactive Command P	rompt	
						onnect to C\$ shares or co onsole as a different user.		ols.
Local P	ath:						Brov	vse
	Software					Save	Cl	

4. **Save** your changes.