Install Recast Proxy Separately

Last Modified on 08.01.23

You can install a Recast Proxy separately if it was not installed during the Recast Management Server installation, or if it needs to be installed on a server other than the Recast Management Server. After installing a Recast Proxy separately, you'll need to approve it manually and add service connections.

For an overview of proxy types, uses, permissions, installation and configuration, see Recast Proxy.

The Recast Proxy SQLite file is located at C:\Users\<Proxy Username>\AppData\Roaming\Recast Software\Recast Proxy

Prerequisites

• Installed Recast Management Server

Run the Proxy Installer

To install Recast Proxy:

1. Download the Recast Proxy installer from the Recast Portal and run it.

2. On the **Recast Server Configuration** page, enter the Recast Management **Server Name** and **Server Port** number.

3. Click **Test Connection** to make sure that the proxy can connect to the Recast Management Server.

🕼 Recast Proxy 4.8.2109.4101 Setup			-		×	
Recast Server Configuration						
	Server Name Server Port	CM1.corp.c	contoso.com			
Success	Test Conne	ection				
			Back	Next	Can	cel

If the installer does not connect to the Recast Management Server, the proxy will not install successfully. Troubleshoot any error messages that appear in the installer before continuing with the install.

4. On the **Service Account Configuration** page, enter the **Domain**, **Username** and **Password** that you would like to use for your proxy and click **Test Credentials** to verify service account details.

Service Account Configuration					
Recast Proxies are used to run Recast actions as a service account rat user running the ConfigMgr console.	ther tha	n the			
Domain corp.contoso.com					
Username LabAdmin					
Password					
Test Credentials					
User credentials valid					
Back Next		Ca	ncel		

If the User Account Credentials that you enter on the Service Account Proxy Screen do not validate correctly, the Service Account Proxy will not work correctly. Troubleshoot any login errors before continuing to the next step.

5. On the **Domain Configuration** page enter your primary **Domain** and click **Test Domain Connection** to check that the service account can read from the domain.

记 Recast Proxy 4.8.2109.4101 Setup -		×
Domain Configuration		
Enter and verify the information necessary to read from your Active Directory domain.		
Domain corp.contoso.com Test Domain Connection		
Success		
Back Next	Car	ncei

6. On the **Configuration Manager Configuration** page, enter your **SMS Provider**, **Site Code**, **SQL Server**, and **SQL Database** information and click **Test ConfigMgr Connection** to check that your service account has permission to access your Configuration Manager environment.

Recast Proxy 4.8.2109.4101 Setup		-		×
Configuration Manager Configuration				
Enter and verify the informati environment.	n necessary to access your Confi	guration Mana	iger	
SMS Provider	CM1.corp.contoso.com			
Site Code	СНQ			
SQL Server	CM1.corp.contoso.com			
SQL Database	ConfigMgr_CHQ			
Test ConfigMgr Con	ection			
Success				
	Back	Next	Cancel	

7. If you have a standalone MBAM server (and are not managing BitLocker in ConfigMgr), enable Configure MBAM and

enter the information for your MBAM environment. If you are not using an MBAM Server, leave the checkbox blank and click **Install**.



8. If you have a standalone MBAM environment, enter its details and click **Test MBAM Connection** to ensure that the service account you selected has permission to use MBAM.

# Recast Proxy 4.8.2109.4101 Setup —				×
MBAM Configuration			[
If you have a standalone MBA to access it.	M server enter and verify the informa	ation neces	sary	
Administration URL SQL Server Compliance Status DB	MBAM Compliance Status			
Recovery & Hardware DB MBAM Recovery and Hardware Test MBAM Connection				
	Back 📢 I	install	Can	cel

9. Click Install.

10. After the installation completes, click **Finish** to close the installer.